ADS5600 User manual

Copyright © ADS TECH All Rights Reserved http://www.adsscan.com



Dear user,

Thank you for purchasing ADS5600(AM-1). This manual contains usage and after service, please read it carefully before using. Now we will take model ADS5802(AM-HARLEY) to illustrate as follows:

CONTENT

I. Member Registration	01
II. Software Installation	03
III. Software Registration	
IV. Software Upgrade	14
V. F.A.Q	17
VI. After Service	

I. Member Registration

Steps 1: Open IE Explorer and visit: http://www.adsscan.com





Steps 2: Click the English language to visit the English version of our official website (Figure-02).





Steps 3: If you do not register, please register first. Click the "register" button (Figure-3), then it will enter the registration interface (Figure-4).





Your Name: Bill Email Address: bill@adsscan.com
Email Address: bill@adsscan.com
bill@adsscan.com * Password:
Password:
Confilm Password:
Tel/Mobile:
0086-0755-89368397
Which one describe you the best?
Online Sales 👻
Company Name:
Automotive Diagnostic Scanner
Enter The Code : 17759 17759

Figure-04

Steps 4: Input info. all above and click "Register" button.

Microsoft	Internet Explorer	X
⚠	Register succefully!!	
	ОК	

Figure-05

Steps 5: Now finish registration, pls login with "Username" and "Password" previously registered (Figure-06).



	se login with your ADS ID and password.
Email Address:	
bill@adsscan.com	
Password:	
Forget Your Password? Enter The Code : 08387	08387
🔁 Login	

Figure-06

II. Software Installation

Note:

Before install the software, pls connect the USB cable between the PC and device and ensure the power indicator light light up.

Steps 1: Open the CD and click "Setup.exe" icon as Figure-07, then right click and select Run button:





Steps 2: Click "Run" button as Figure-08:

1	Name: setup.exe
	Publisher: Unknown Publisher
	Type: Application
	From: C:\Documents and Settings\Administrator\Desktop
🔽 Al <u>w</u> ays a	<u>R</u> un Cancel

Figure-08

Steps 3: Click "Next" button as Figure-09:





Figure-09

Steps 4: Click "Next" button again as Figure-10:

🛃 AM-HD(EN) Setup	
Select Installation Folder This is the folder where AM-HD(EN) will be installed.	
To install in this folder, click "Next". To install to a different fol "Browse".	der, enter it below or click
Eolder: C:\Program Files\ADS-TECH\AM-HD(EN)\	Browse
AM-HD(EN) Inst	Next > Cancel

Figure-10 **Steps 5:** Click "Install" button as Figure-11:





Figure-11

Steps 6: It will required to install the USB driver as Figure-12:





Steps 7: Click "OK" button after USB driver installation as Figure-13:



Figure-13 **Steps 8:** Click "Finish" button as Figure-14:





Figure-14

Steps 9: Software installation successful, it will display two icons in the desktop:



Figure-15

Note:

1) If your PC has installed the firewall or anti-virus software, it will prevent the diagnostic software running. Pls uninstall and try it again.

2) If your PC doesn't work with CD, pls go to our website and click the "Upgrade" interface to download the software.



Automotive Diagnostic Scanner					S.	Sign in Registre	
Home	Product	Upgrade	Manuals	News	About ADS	Contact ADS	SEARCH
Auto Diag	g Series	Motor D	iag Series	Truck	Diag Series	Diag Cable Series	
= ADS160	00	= ADS58	301	= ADS	3100	= ADS3500	
= ADS12	00	= ADS58	302			= ADS3501	
= ADS11	00	= ADS53	301			= ADS3502	
		= ADS53					

Figure-16

III. Software Registration

Note:

If it is the first time you start AM-HARLEY diagnostic system, it needs to be registered, or can't scan. Before register user, pls connect the PC and USB cable with 12V power supply and available Internet.

Steps 1: Double click and start "AM-HD(EN)" on the desktop as Figure-17:





Steps 2: Click "REGISTER" button as Figure-18:





Figure-18

Steps 3: Click "OK" button as Figure-19, it will display interface as Figure-20:



Figure-19





Figure-20

Steps 4: Turn to website and sign in your registered account:



Figure-21



Returning Gue	sts
lf you have an a	account,please login with your ADS ID and password.
Email Address	:
bill@adsscan.co	m
Password:	
•••••	
🕒 Login	
	Figure-22
	Microsoft Internet Explorer
	Dear Bill, welcome to ADS TECH!!
	OK

Steps 5: Enter "Get Registration Code" from background interface:



My Account	
Modify Passwords	
Get Registration Code	
Upload your Series Number	
Logout	

Figure-24

Steps 6: Put the Product Code and Rand Code into the forms and click "Register" button to get the Password.

If you want to get your registration code,please follow up the informati	ons.
Product Code:	
346987949	
Rand code:	
HMXNQLFEEH	



Figure-25

Steps 7: Put the Password into the software and click "OK" button.



Figure-26

Steps 8: Click "OK" button as Figure-27:



Figure-27

Steps 9: Register successfully, it will automatically restart as Figure-28:





Figure-28

IV. Software Upgrade

Steps 1: Double click AM-HD(EN) from the desktop as Figure-29:



Figure-29







Figure-30

Steps 3: Click "OK" button as Figure-31, and wait for check:



Figure-32





Steps 4: Put the Password and click "OK" button as Figure-33:

Figure-33

Steps 5: Click "Update" button and after finish, it will auto-logout and restart.

	0:	
Downloadi update progress:	ng: 0%	
	update	

Figure-34

Note: If it is the latest version, it will notice as follows:





Figure-35

V. F.A.Q.

1. If it displays as Figure-36 and still display after reoperate:



Figure-36

Possible problems:

- 1) Check the USB cable connection is reliable between the PC and device.
- 2) Check the USB driver software installation is correct.
- 3) Check the power indicator light of device if lit up.

2. If the USB driver install successfully, it will display in Computer Management as Figure-37:





Figure-37

3. Manually install USB driver:



Steps 1: Right click "My Computer" and click "Properties" as Figure-38:



Figure-38

Steps 2: Click "Hardware" button as Figure-39:

e Hardware	Advanced
sts all the hardware device the Device Manager to cl e.	
Device Ma	anager
make sure that installed di ws. Windows Update lets s to Windows Update for	you set up
Windows L	Jpdate
de a way for you to set up igurations.	and store
Hardware	Profiles
	the Device Manager to cl e. Device M. make sure that installed di ws. Windows Update lets s to Windows Update for Windows Update for Windows L de a way for you to set up igurations.



Figure-39

Steps 3: Click "Device Manager" button and it will display as Figure-40:



Figure-40

Steps 4: Double click the blue dash area and select "Update Driver...":



Figure-41

Steps 5: Click "Next" button as Figure-42:





Figure-42





Figure-43

Hardware Update Wizard	
Please wait while the wizard sear	ches
CP2102 USB to UART Br	idge Controller
	<u>S</u>
	K Back Next > Cancel

Steps 7: Then wait for wizard search as Figure-44:

Figure-44

Steps 8: If it display as Figure-45, pls click "Continue Anyway":



Figure-45



Steps 9: Click "Finish" button and USB driver will display as Figure-46:



Figure-46



Figure-47



VI. After service

- 1. Guarantee period: One year warranty.
- 2. URL: http://www.adsscan.com
- 3. Phone: +86-755-89368397
- 4. E-mail: sales@adsscan.com