VVDI2 – Install Software and Driver

Table of Contents

1.	Docu	ment Declaration	 3
2.	Instal	l software	 4
3.	Instal	Driver	 8
	3.1.	Manual Install Driver	 8

1.Document Declaration

Please view the following declaration carefully:

- VVDI2 Install Software and Driver can help you install software and VVDI2 driver.
 Please DON'T used for illegal purpose, Please follow the national law
- VVDI2 Install Software and Driver is written by VVDI2, please DON'T used for commercial purposes without authorize
- Install driver and set latency timer is very important, please view carefully
- Any illegal use VVDI2 Install Software and Driver, illegal use VVDI2 device, The user should take all risks, the company does not assume any responsibility

2.Install software

Install software is very easy, just follow the window. Show with window steps:



VVDI2 – Install Software and Driver



🗢 VVDI2 Setup	Advancedili	▶ Installe
Device Driver Installation V	Vizard Wizard Welcome to the Device Driver Installation Wizard! This wizard helps you install the software drivers that some computers devices need in order to work.	installe
	To continue, click Next.	
	< Back Next > Cancel	

Attention: If you are install VVDI2 software (any version) for first time, you need choose NEXT, else you can choose CANCEL

Device Driver Installation	Wizard
	Completing the Device Driver Installation Wizard
	The drivers were successfully installed on this computer.
	Driver Name Status
	 FTDI CDM Driver Packa Device Updated FTDI CDM Driver Packa Device Updated
7)	< Back Finish Cancel



Install complete. There will be a quick start on your desktop



3. Install Driver

- Generally, VVDI2 driver can install automatically with install software.
- If install driver failed or your programs can not connect to VVDI2, you need manual install driver accord chapter 3.1

3.1. Manual Install Driver

Open Device Manager: Open windows explorer, right click "My computer" and select "Properties" (PICTURE 3. 1), open "System properties" (PICTURE 3. 2), select "Hardware" -> "Device Manager", Open Device Manager (PICTURE 3. 3)



(PICTURE 3.1)

stem Pro	operties			?	
Syster	n Restore	Automa	tic Updates	Remote	1
General	Compu	iter Name	Hardware	Advanced	1
- Device I	Manager The Device M on your compu properties of ar	ter. Use the De	the hardware device evice Manager to ch Device Ma	hange the	
- Drivers-	compatible with	n Windows. Wi connects to W	sure that installed dr ndows Update lets indows Update for Windows U	you set up drivers.	
Hardwar	re Profiles Hardware profi different hardw		ay for you to set up	and store	
			Hardware	Profiles	



- (PICTURE 3. 3)
- Install bus driver: Disconnect other USB cable from PC(Mouse and keyboard should keep connect)
 - VVDI2 install with other version drivers: In (<u>PICTURE 3.3</u>) select "Universal Serial Bus controllers" -> "USB Serial Converter", double click on it, get properties window(<u>PICTURE 3.4</u>)

View "**Driver**" page: "**Driver Date**" should be: **3/18/2011**, "**Driver Version**" should be: **2.8.14.0**(<u>PICTURE 3.11</u>). If all right, don't install driver again. If not shown as before, you need install driver with following steps:

- In (<u>PICTURE 3.4</u>), select "Driver" -> "Update Driver". Open "Hardware Update Wizard" (<u>PICTURE 3.5</u>)
- In (<u>PICTURE 3.5</u>), select "Install from a list or specific location (Advanced)", next to get window (<u>PICTURE 3.6</u>)
- In (<u>PICTURE 3.6</u>), select "Don't' search. I will choose the driver to install." next to get window (<u>PICTURE 3.7</u>). Sometimes you will get (<u>PICTURE 3.8</u>) directly, at this situation, go to step 5)
- 4) In (<u>PICTURE 3.7</u>), select "Universal Serial Bus controllers", next to get window (<u>PICTURE 3.8</u>)

- 5) In (<u>PICTURE 3.8</u>), select "Have Disk...", get install from disk window (<u>PICTURE 3.9</u>)
- 6) In <u>(PICTURE 3.9)</u>, input absolute path for USB Driver folder in install directory (Browse... and choose install directory, or you can find the path from Start->Programs->VVDI2->USB Drivers). Press OK and wait complete. Sometimes system will ask again for Are you sure to install this driver? Continue is need

USB Serial Converter Properties		?×
General Advanced Driver Details		
USB Serial Converter		
Driver Provider: FTDI		
Driver Date: 1/27/2014		
Driver Version: 2.10.0.0		
Digital Signer: Not digitally	i signed	
Driver Details To view detai	Is about the driver files.	
Update Driver To update the	e driver for this device.	
	ails after updating the driver, r eviously installed driver.	roll
Uninstall To uninstall th	e driver (Advanced).	
ОК	Cancel H	elp
	(PICTURE 3, 4)	



Please choose your search and installation options.
Search for the best driver in these locations. Use the check boxes below to limit or expand the default search, which includes local sector and expression to be best drives formed will be installed.
paths and removable media. The best driver found will be installed. Search removable media (floppy, CD-ROM) Include this location in the search: Browse
Don't search. I will choose the driver to install. Choose this option to select the device driver from a list. Windows does not guarantee that the driver you choose will be the best match for your hardware.
< <u>B</u> ack <u>N</u> ext > Cancel
(PICTURE 3.6)





(PICTURE 3.8)

Ver: 1.0



VVDI2 is not recognized: you can find VVDI2(with yellow !) in "Other devices" list from device manager (PICTURE 3.10), double click get properties window. Then install driver accord VVDI2 install with other version drivers



(PICTURE 3.10)

 Verify Bus Driver: Open properties window after install driver, view Driver page: "Driver Date" should be: 3/18/2011, "Driver Version" should be: 2.8.14.0(<u>PICTURE</u> 3.11)

USB Serial Converter Properties 🛛 🛛 🛛 🥐 🔀
General Advanced Driver Details
USB Serial Converter
Driver Provider: FTDI
Driver Date: 3/18/2011
Driver Version: 2.8.14.0
Digital Signer: Microsoft Windows Hardware Compatibility Publ
Driver Details To view details about the driver files.
Update Driver To update the driver for this device.
Roll Back Driver If the device fails after updating the driver, roll back to the previously installed driver.
Uninstall To uninstall the driver (Advanced).
OK Cancel Help
<u>(PICTURE 3. 11)</u>

